



**Note:** This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=0EH

## Version

1 and higher

## Brief

SELECT DEFAULT DRIVE

## Family API

[DosSelectDisk](#)

## Input

```
AH = 0Eh
DL = new default drive (00h = A:, 01h = B:, etc)
```

## Return

AL = number of potentially valid drive letters

## Notes

under Novell NetWare, the return value is always 32, the number of drives that NetWare supports

under DOS 3.0+, the return value is the greatest of 5, the value of LASTDRIVE= in CONFIG.SYS, and the number of drives actually present on a DOS 1.x/2.x single-floppy system, AL returns 2 since the floppy may be accessed as either A: or B: otherwise, the return value is the highest drive actually present

DOS 1.x supports a maximum of 16 drives, 2.x a maximum of 63 drives, and 3+ a maximum of 26 drives

under Novell DOS 7, this function returns the correct LASTDRIVE value even when the undocumented LASTDRIVE=27..32 directive was used in CONFIG.SYS

“parse FCB” (see AH=29h) can be used to determine whether a drive letter is valid

## See also

AH=19h,AH=3Bh,AH=DBh

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| <b>DOS API</b>              |                                                                                                                                                                                                                                                                                                                                                            |
|-----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Process manager             | INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H                                                                                                                                                                                                                                  |
| File manager                | INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O        | INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH                                                                                                                                                                                                                                      |
| Signals                     | INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H                                                                                                                                                                                                                                                                                                     |
| Memory manager              | <b>INT 21H</b> : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H                                                                                                                                                                                                                                                                                                 |
| Date and Time               | <b>INT 21H</b> : 2AH, 2BH, 2CH, 2DH                                                                                                                                                                                                                                                                                                                        |
| Misc                        | <b>INT 21H</b> : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H                                                                                                                                                                                                                                                                                               |
| NLS                         | <b>INT 21H</b> : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H                                                                                                                                                                    |
| Devices                     | <b>INT 21H</b> : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H                                                                                                                                                                                                         |
| Network                     | <b>INT 21H</b> : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H                                                                                                                                                                                                                                          |
| <b>osFree Macro Library</b> |                                                                                                                                                                                                                                                                                                                                                            |
| Video I/O                   | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls                                                                                                                                         |
| Hardware info               | @Equipment @MemSize                                                                                                                                                                                                                                                                                                                                        |
| Serial I/O                  | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus                                                                                                                                                                                                                                                                                                           |
| Tape I/O                    | @TapeOn @TapeOff @TapeRead @TapeWrite                                                                                                                                                                                                                                                                                                                      |
| Keyboard I/O                | @KbdStatus @CharIn @CharPeek                                                                                                                                                                                                                                                                                                                               |

**osFree Macro Library**

|                |                                                                            |
|----------------|----------------------------------------------------------------------------|
| Printer I/O    | @PrnPrint @PrnInit @PrnStatus                                              |
| Disk I/O       | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat              |
| Date and Time  | @SetTime @GetTime                                                          |
| Mouse          | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey<br>@MouRegion |
| Memory manager | @ModBlok SET_BLOCK                                                         |

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

**Family API**

|           |                 |                                                                                                                                                                                                                                                                                                                                                                                             |
|-----------|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS       | Process Manager | DosBeep DosExit DosSleep DosExecPgm                                                                                                                                                                                                                                                                                                                                                         |
|           | File Manager    | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove<br>DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead<br>DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose<br>DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks<br>DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo<br>DosShutdown |
|           | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg<br>DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias                                                                                                                                                                                                                                                       |
|           | NLS             | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate<br>DosGetMessage DosInsMessage DosPutMessage                                                                                                                                                                                                                                                                            |
|           | Date and Time   | DosSetDateTime DosGetDateTime                                                                                                                                                                                                                                                                                                                                                               |
|           | Devices         | DosDevConfig DosDevIOctl DosDevIOctl2                                                                                                                                                                                                                                                                                                                                                       |
|           | Signals         | DosHoldSignal DosSetSigHandler                                                                                                                                                                                                                                                                                                                                                              |
|           | Misc            | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass<br>DosSetVec                                                                                                                                                                                                                                                                                                      |
| KBD       |                 | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek                                                                                                                                                                                                                                                                                                                      |
| VIO       |                 | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf<br>VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt<br>VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf<br>VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell<br>VioWrtNChar VioWrtTTY VioScrLock VioPopUp                                           |
| Tools     |                 | BIND                                                                                                                                                                                                                                                                                                                                                                                        |
| Modules   |                 | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL                                                                                                                                                                                                                                                                                                                                              |
| Libraries |                 | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB                                                                                                                                                                                                                                                                                                                                       |

2018/08/25 15:05 · prokushev · 0 Comments

From:

<http://185.82.219.184/doku/> - **osFree wiki**

Permanent link:

<http://185.82.219.184/doku/doku.php?id=en:docs:dos:api:int21:0e&rev=1607331393>Last update: **2020/12/07 08:56**