



**Note:** This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=34H

## Version

2 and higher

## Brief

GET ADDRESS OF INDOS FLAG

## Family API

## Input

AH = 34h

## Return

ES:BX → one-byte InDOS flag

## Notes

this function executes on the DOS stack, and thus cannot be called while another DOS function is already executing; you should use this function once at the beginning of the program and store the returned pointer rather than calling it when requiring DOS access

the value of InDOS is incremented whenever an INT 21 function begins and decremented whenever one completes

during an INT 28 call, it is safe to call some INT 21 functions even though InDOS may be 01h instead of zero

InDOS alone is not sufficient for determining when it is safe to enter DOS, as the critical error handling

decrements InDOS and increments the critical error flag for the duration of the critical error. Thus, it is possible for InDOS to be zero even if DOS is busy.

SMARTDRV 4.0 sets the InDOS flag while flushing its buffers to disk, then zeros it on completion

the critical error flag is the byte immediately following InDOS in DOS 2.x, and the byte BEFORE the InDOS flag in DOS 3.0+ and DR DOS 3.41+ (except COMPAQ DOS 3.0, where the critical error flag is located 1AAh bytes BEFORE the critical section flag)

for DOS 3.1+, an undocumented call exists to get the address of the critical error flag (see AX=5D06h)

this function was undocumented prior to the release of DOS 5.0.

See also

AX=5D06h,AX=5D0Bh,INT 15/AX=DE1Fh,INT 28

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| DOS API              |                                                                                                                                                                                                                                                                                                                                                            |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Process manager      | INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H                                                                                                                                                                                                                                  |
| File manager         | INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O | INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH                                                                                                                                                                                                                                      |
| Signals              | INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H                                                                                                                                                                                                                                                                                                     |
| Memory manager       | <b>INT 21H</b> : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H                                                                                                                                                                                                                                                                                                 |
| Date and Time        | <b>INT 21H</b> : 2AH, 2BH, 2CH, 2DH                                                                                                                                                                                                                                                                                                                        |
| Misc                 | <b>INT 21H</b> : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H                                                                                                                                                                                                                                                                                               |
| NLS                  | <b>INT 21H</b> : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H                                                                                                                                                                    |
| Devices              | <b>INT 21H</b> : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H                                                                                                                                                                                                         |
| Network              | <b>INT 21H</b> : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H                                                                                                                                                                                                                                          |

## osFree Macro Library

|                |                                                                                                                                                                                                                    |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Video I/O      | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info  | @Equipment @MemSize                                                                                                                                                                                                |
| Serial I/O     | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus                                                                                                                                                                   |
| Tape I/O       | @TapeOn @TapeOff @TapeRead @TapeWrite                                                                                                                                                                              |
| Keyboard I/O   | @KbdStatus @CharIn @CharPeek                                                                                                                                                                                       |
| Printer I/O    | @PrnPrint @PrnInit @PrnStatus                                                                                                                                                                                      |
| Disk I/O       | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat                                                                                                                                                      |
| Date and Time  | @SetTime @GetTime                                                                                                                                                                                                  |
| Mouse          | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion                                                                                                                                            |
| Memory manager | @ModBlok SET_BLOCK                                                                                                                                                                                                 |

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

## Family API

|           |                 |                                                                                                                                                                                                                                                                                                                                                                              |
|-----------|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS       | Process Manager | DosBeep DosExit DosSleep DosExecPgm                                                                                                                                                                                                                                                                                                                                          |
|           | File Manager    | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
|           | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias                                                                                                                                                                                                                                           |
|           | NLS             | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage                                                                                                                                                                                                                                                                |
|           | Date and Time   | DosSetDateTime DosGetDateTime                                                                                                                                                                                                                                                                                                                                                |
|           | Devices         | DosDevConfig DosDevIOCtl DosDevIOCtl2                                                                                                                                                                                                                                                                                                                                        |
|           | Signals         | DosHoldSignal DosSetSigHandler                                                                                                                                                                                                                                                                                                                                               |
|           | Misc            | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec                                                                                                                                                                                                                                                                                          |
| KBD       |                 | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek                                                                                                                                                                                                                                                                                                       |
| VIO       |                 | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp                                        |
| Tools     |                 | BIND                                                                                                                                                                                                                                                                                                                                                                         |
| Modules   |                 | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL                                                                                                                                                                                                                                                                                                                               |
| Libraries |                 | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB                                                                                                                                                                                                                                                                                                                        |

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:34>

Last update: **2024/05/02 05:50**

