2025/10/29 23:07 1/3 Int 2FH, AH=16H, AL=87H



#### Note: This API calls are shared between DOS and Win16 personality.

DPMI is a shared interface for DOS applications to access Intel 80286+ CPUs services. DOS DMPI host provides core services for protected mode applications. Multitasking OS with DOS support also provides DMPI in most cases. Windows standard and extended mode kernel is a DPMI client app. Standard and extended mode kernel differs minimally and shares common codebase. Standard Windows kernel works under DOSX extender. DOSX is a specialized version of 16-bit DPMI Extender (but it is standard DPMI host). Standard mode is just DPMI client, exnhanced mode is DPMI client running under Virtual Machime Manager (really, multitasker which allow to run many DOS sessions). Both modes shares DPMI interface for kernel communication. The OS/2 virtual DOS Protected Mode Interface (VDPMI) device driver provides Version 0.9 DPMI support for virtual DOS machines. Win16 (up to Windows ME) provides Version 0.9 DPMI support. Windows in Standard Mode provides DPMI services only for Windows Applications, not DOS sessions.

DPMI host often merged with DPMI extender. Usually DPMI extender provide DPMI host standard services and DOS translation or True DPMI services.

2021/08/05 10:15 · prokushev · 0 Comments

# Int 2FH, AH=16H, AL=87H

## **Version**

0.9

# **Brief**

Obtain Real-to-Protected Mode Switch Entry Point

# Input

• AX = 1687h

### Return

If function successful
AX = 0
BX = flags

#### Last update: 2023/03/25 10:38

Bit	Significance	
10	0 = 32-bit programs are not supported	
	1 = 32-bit programs are supported	
1-15	not used	

#### CL = processor type

Value	Significance
02H	80286
03H	80386
04H	80486
05H-FFF	Reserved for future Intel processors

```
DH = DPMI major version as a decimal number (represented in binary)
DL = DPMI minor version as a decimal number (represented in binary)
SI = number of paragraphs required for DPMI host private data (may be 0)
ES:DI = segment:offset of procedure to call to enter protected mode
if function unsuccessful (no DPMI host present)
AX = nonzero
```

### **Notes**

This function can be called in real mode only to test for the presence of a DPMI host, and to obtain an address of a mode switch routine that can be called to begin execution in protected mode.

The entry point returned by Int 2FH Function 1687H is only called for the first switch to protected mode by a DPMI client. For further details on the protocol for switching to protected mode and the environment after switching to protected mode, see Client Initialization.

Under DPMI hosts, the major version number is returned in DH and the minor version number is returned in DL. There are two decimal digits for the minor version number with the least-significant digit representing the revision number of the minor version number. Under DPMI version 0.9 hosts, DH is returned as 0, and DL is returned as decimal 90 (5AH). In hypothetical DPMI version 2.3, DH would be returned as 2 and DL would be returned as 30 (1EH).

# See also

## **Note**

Text based on http://www.delorie.com/djgpp/doc/dpmi/

DPMI				
Process manager	INT 2FH 1680H, 1687H			
Signals				
Memory manager				

http://osfree.su/doku/ Printed on 2025/10/29 23:07

2025/10/29 23:07 3/3 Int 2FH, AH=16H, AL=87H

DPMI				
Misc	INT 2FH 1686H, 168AH			
Devices				

2021/08/13 14:23 · prokushev · 0 Comments

From:

http://osfree.su/doku/ - osFree wiki

Permanent link:

http://osfree.su/doku/doku.php?id=en:docs:dpmi:api:int2f:16:87

Last update: 2023/03/25 10:38

