



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

DosPutMessage

This call outputs the message in a buffer passed by a caller to the specified handle. The function formats the buffer to prevent words from wrapping if displayed to a screen.

Syntax

```
DosPutMessage (FileHandle, MessageLength, MessageBuffer)
```

Parameters

- FileHandle ([USHORT](#)) - input : Handle of the output file or device.
- MessageLength ([USHORT](#)) - input : Length of the message to be output.
- MessageBuffer ([PCHAR](#)) - input : Address of the buffer that contains the returned message.

Return Code

rc ([USHORT](#)) - return

Return code descriptions are:

- 0 NO_ERROR
- 6 ERROR_INVALID_HANDLE
- 19 ERROR_WRITE_PROTECT
- 321 ERROR_MR_UN_PERFORM

Remarks

Screen width is assumed to be 80 characters. The DosPutMessage call counts a CR/LF in the 80 characters that it tries to write to the screen. If a word extends past column 78, it is put on the next line. DosPutMessage assumes the starting cursor position is column one when handling a word wrap.

If the last character to be positioned on a line is a double-byte character that would be bisected, the

rule above ensures that the character is not bisected.

Example Code

C Binding

```
#define INCL_DOSMISC

USHORT rc = DosPutMessage(FileHandle, MessageLength, MessageBuffer);

USHORT FileHandle; /* Handle of output file/device */
USHORT MessageLength; /* Length of message buffer */
PCHAR MessageBuffer; /* Message buffer */

USHORT rc; /* return code */
```

MASM Binding

```
EXTRN DosPutMessage:FAR
INCL_DOSMISC EQU 1

PUSH WORD FileHandle ;Handle of output file/device
PUSH WORD MessageLength ;Length of message buffer
PUSH@ OTHER MessageBuffer ;Message buffer
CALL DosPutMessage
```

Returns WORD

Note

Text based on [http://www.edm2.com/index.php/DosPutMessage_\(FAPI\)](http://www.edm2.com/index.php/DosPutMessage_(FAPI))

Family API	
DOS	Process Manager DosBeep DosExit DosSleep DosExecPgm
	File Manager DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time DosSet Date Time DosGet Date Time
	Devices DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals DosHoldSignal DosSet Sig Handler
	Misc BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD	KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO	VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt VioScr Un Lock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf VioWrt Cell Str VioWrt Char Str VioWrt Char Str Att VioWrt N Attr VioWrt N Cell VioWrt N Char VioWrt TTY VioScr Lock VioPop Up
Tools	BIND
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://ftp.osfree.org/doku/> - osFree wiki

Permanent link:
<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:dosputmessage>



Last update: **2021/09/17 06:37**