



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## MouGetPtrShape

This call allows a process to get (copy) the pointer shape for the session.

### Syntax

```
MouGetPtrShape (PtrBuffer, PtrDefRec, DeviceHandle)
```

### Parameters

- PtrBuffer (PBYTE) - output: Address of an area in application storage where the pointer draw device driver returns the pointer bit image. See MouSetPtrShape for a further description of the resulting content of this buffer.
- PtrDefRec (PPTRSHAPE) - input/output: Address of a structure in application storage where the application stores the data necessary for the pointer device driver to return information about the Row by Col image for each bit plane for the mode the display is currently running. See MouSetPtrShape for a further description of the contents of this structure.
  - TotLength (USHORT) : Length of the pointer buffer available for the pointer device driver to build a Row by Col image for each bit plane for the mode the display is currently running. This value is supplied by the application. If the value is too small, pointer draw places the true length of the image in this field, and returns an error.
  - col (USHORT)

Number of columns in the mouse shape. In graphics modes, this field contains the pel width (columns) of the mouse shape for the session and must be greater than or equal to 1. In text modes, col must equal 1.

- row (USHORT)

Number of rows in the mouse shape. In graphics modes, this field contains the pel height (rows) of the mouse shape for the session and must be greater than or equal to 1. In text modes, row must equal 1.

- coloffset (USHORT)

This value is returned by the mouse device driver to indicate the relative column offset within the pointer image. The value defines the center (hotspot) of the pointer image. This value is a signed number that represents either character or pel offset, depending on the display mode.

- rowoffset (USHORT)

This value is returned by the mouse device driver to indicate the relative row offset within the pointer image. The value defines the center (hotspot) of the pointer image. This value is a signed number that represents either character or pel offset, depending on the display mode.

- DeviceHandle (HMOU) - input:Handle of the mouse device from a previous MouOpen.

For all OS/2 system-supported modes, TotLength is specified in bytes and is equal to:

- Mono & Text Modes
  - For text mode height and width must be 1, so length is always 4.

```
TotLength = (height in chars) * (width in chars) * 2 * 2
          = 1 * 1 * 2 * 2
          = 4
```

- Graphics Mode
  - Width-in-pels must be a multiple of 8.
  - $\text{TotLength} = (\text{height in pels}) * (\text{width in pels}) * (\text{bits per pel}) * 2 / 8$
- Modes 4 and 5 (320 X 200)
  - $\text{TotLength} = (\text{height}) * (\text{width}) * 2 * 2 / 8$
- Mode 6 (640 X 200)
  - $\text{TotLength} = (\text{height}) * (\text{width}) * 1 * 2 / 8$

Length calculations produce byte boundary buffer sizes.

## Return Code

rc (USHORT) - return

Return code descriptions are:

- 0 NO\_ERROR
- 385 ERROR\_MOUSE\_NO\_DEVICE
- 387 ERROR\_MOUSE\_INV\_PARMS
- 466 ERROR\_MOU\_DETACHED
- 501 ERROR\_MOUSE\_NO\_CONSOLE
- 505 ERROR\_MOU\_EXTENDED\_SG

## Remarks

The application passes a parameter list with the same meaning as defined for [MouSetPtrShape](#) to the mouse device driver. The mouse device driver copies the parameters that describe the pointer shape and attributes into the pointer definition control block pointed to by the PtrDefRec parameter. The word 0 (buffer length = TotLength) pointer definition record parameter field must contain the size in bytes of the application buffer where the device driver is to insert the sessions pointer image. All other words in the parameter list are returned to the application by MouGetPtrShape.

If the buffer size is insufficient, the TotLength field contains the actual size in bytes of the returned pointer image.

The pointer shape may be set by the application with MouSetPtrShape or may be the default image provided by the installed Pointer Device Driver.

## Bindings

### C

```

typedef struct _PTRSHAPE { /* moups */
    USHORT cb;           /* total length necessary to build image */
    USHORT col;          /* # of columns in mouse shape */
    USHORT row;          /* number of rows in mouse shape */
    USHORT colHot;       /* column coordinate of pointer image hotspot */
    USHORT rowHot;       /* row coordinate of pointer image hotspot */
} PTRSHAPE;

#define INCL_MOU

USHORT rc = MouGetPtrShape(PtrBuffer, PtrDefRec, DeviceHandle);

PBYTE     PtrBuffer;      /* Pointer shape buffer */
PPTRSHAPE PtrDefRec;     /* Pointer definition struct */
HMOU      DeviceHandle;   /* Mouse device handle */

USHORT     rc;            /* return code */

```

### MASM

```

PTRSHAPE struc
    moups_cb      dw ? ;total length necessary to build image
    moups_col     dw ? ;# of columns in mouse shape
    moups_row     dw ? ;number of rows in mouse shape
    moups_colHot  dw ? ;column coordinate of pointer image hotspot
    moups_rowHot  dw ? ;row coordinate of pointer image hotspot
PTRSHAPE ends

EXTRN MouGetPtrShape:FAR
INCL_MOU        EQU 1

PUSH@ OTHER     PtrBuffer      ;Pointer shape buffer
PUSH@ OTHER     PtrDefRec     ;Pointer definition struct
PUSH WORD       DeviceHandle  ;Mouse device handle
CALL  MouGetPtrShape

```

Returns WORD

**Family API**

DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS	DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time	DosSet Date Time DosGet Date Time
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHold Signal DosSet Sig Handler
	Misc	BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD		KbdCharIn KbdFlush Buffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO		VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt VioScr Un Lock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf VioWrt Cell Str VioWrt Char Str VioWrt Char Str Att VioWrt N Attr VioWrt N Cell VioWrt N Char VioWrt TTY VioScr Lock VioPop Up
Tools		BIND
Modules		DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:

<http://ftp.osfree.org/doku/> - osFree wiki

Permanent link:

<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:mougetptrshape>

Last update: 2021/11/04 13:11