



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

# VioGetCurType

## Syntax

```
VioGetCurType (CursorData, VioHandle)
```

## Parameters

- CursorData ([PVIOCURSORINFO](#)) - output : Address of the cursor characteristics structure:
  - startline ([USHORT](#)) : Horizontal scan line in the character cell that marks the top line of the cursor. If the character cell has n scan lines, 0 is the top scan line of the character cell and (n-1) is the bottom scan line.
  - endline ([USHORT](#)) : Horizontal scan line in the character cell that marks the bottom line of the cursor. Scan lines within a character cell are numbered as defined in startline.
  - cursorwidth ([USHORT](#)) : Width of the cursor. In text modes, cursorwidth is the number of columns. The maximum number supported by the OS/2 base video subsystem is 1. In graphics modes, cursorwidth is the number of pels.
  - cursorattrib ([USHORT](#)) : A value of -1 denotes a hidden cursor, all other values in text mode denote normal cursor and in graphics mode denote color attribute.
- VioHandle ([HVIO](#)) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

## Return Code

rc ([USHORT](#)) - return

Return code descriptions are:

- 0 NO\_ERROR
- 355 ERROR\_VIO\_MODE
- 436 ERROR\_VIO\_INVALID\_HANDLE
- 465 ERROR\_VIO\_DETACHED

## Remarks

If CursorStartLine and CursorEndLine were originally specified as percentages on [VioSetCurType](#) (using negative values), the positive values into which they were translated are returned. Refer to [VioSetCurType](#) for more information on how percentages can be used to set CursorStartLine and CursorEndLine independent of the number of scan lines per character cell.

## Family API Considerations

In DOS mode, VioGetCurType returns only two values for cursorattrib: 0 = visible cursor, and -1 = hidden cursor.

## Bindings

### C Binding

```
typedef struct _VIOCURSORINFO { /* vioci */
    USHORT   yStart;           /*cursor start line */
    USHORT   cEnd;            /* cursor end line */
    USHORT   cx;              /* cursor width */
    USHORT   attr;            /* -1=hidden cursor, any other=normal
                               cursor */
} VIOCURSORINFO;

#define INCL_VIO

USHORT rc = VioGetCurType(CursorData, VioHandle);

P_VIOCURSORINFO CursorData; /* Cursor characteristics */
H_VIO VioHandle; /* Vio handle */

USHORT rc; /* return code */
```

### MASM Binding

```
VIOCURSORINFO struc
    vioci_yStart dw ? ;cursor start line
    vioci_cEnd dw ? ;cursor end line
    vioci_cx dw ? ;cursor width
    vioci_attr dw ? ;-1=hidden cursor, any other=normal cursor
VIOCURSORINFO ends

EXTRN VioGetCurType:FAR
INCL_VIO EQU 1
```

```
PUSH@ OTHER CursorData ;Cursor characteristics
PUSH WORD VioHandle ;Vio handle
CALL VioGetCurType
```

Returns **WORD**

## Note

Text based on [http://www.edm2.com/index.php/VioGetCurType\\_\(FAPI\)](http://www.edm2.com/index.php/VioGetCurType_(FAPI))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · 0 Comments

From: <http://osfree.org/doku/> - **osFree wiki**

Permanent link: <http://osfree.org/doku/doku.php?id=en:docs:fapi:viogetcurtype>

Last update: **2021/09/19 02:14**

