



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

# VioReadCellStr

This call reads a string of character-attribute pairs (cells) from the screen, starting at the specified location.

## Syntax

```
VioReadCellStr (CellStr, Length, Row, Column, VioHandle)
```

## Parameters

- CellStr ([PCH](#)) - output : Address of the buffer where the cell string is returned.
- Length ([USHORT](#)) - input/output : Address of the buffer length in bytes. Length must take into account that each character-attribute(s) entry in the buffer is 2 or 4 bytes. If the length of the buffer is not sufficient, the last entry is not complete.
- Row ([USHORT](#)) - input : Starting row of the field to read, 0 is the top row.
- Column ([USHORT](#)) - input : Starting column of the field to read, 0 is the leftmost column.
- VioHandle ([HVIO](#)) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by [VioGetPs](#).

## Return Code

## Remarks

If a string read comes to the end of the line and is not complete, the string read continues at the beginning of the next line. If the read comes to the end of the screen and is not complete, the read terminates and the length is set to the length of the buffer that was filled.

## PM Considerations

[VioReadCellStr](#) reads a string of character/attributes (or cells) from the Advanced VIO presentation space starting at the specified location.

# Bindings

## C Binding

```
#define INCL_VIO

USHORT rc = VioReadCellStr(CellStr, Length, Row, Column, VioHandle);

PCH          CellStr;      /* Cell string buffer */
USHORT       Length;       /* Length of cell string buffer */
USHORT       Row;         /* Starting row location */
USHORT       Column;      /* Starting column location */
HVI0         VioHandle;   /* Video handle */

USHORT       rc;          /* return code */
```

## MASM Binding

```
EXTRN VioReadCellStr:FAR
INCL_VIO EQU 1

PUSH@ OTHER CellStr      ;Cell string buffer
PUSH@ WORD  Length       ;Length of cell string buffer
PUSH WORD  Row           ;Starting row location
PUSH WORD  Column        ;Starting column location
PUSH WORD  VioHandle    ;Video handle
CALL  VioReadCellStr
```

Returns WORD

## Note

Text based on [http://www.edm2.com/index.php/VioReadCellStr\\_\(FAPI\)](http://www.edm2.com/index.php/VioReadCellStr_(FAPI))

| Family API |   |
|------------|---|
| DOS        | Process Manager<br>DosBeep DosExit DosSleep DosExecPgm  |
|            | File Manager<br>DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove<br>DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead<br>DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose<br>DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks<br>DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo |
|            | Memory Manager<br>DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg<br>DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias   |
|            | NLS<br>DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate<br>DosGet Message DosIns Message DosPut Message  |
|            | Date and Time<br>DosSet Date Time DosGet Date Time  |
|            | Devices<br>DosDevConfig DosDevIOCtl DosDevIOCtl2  |
|            | Signals<br>DosHoldSignal DosSet Sig Handler   |
|            | Misc<br>BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class<br>DosSet Vec  |
| KBD        | KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek  |
| VIO        | VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf<br>VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt<br>VioScrUnLock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf<br>VioWrt Cell Str VioWrt Char Str VioWrt Char Str Att VioWrt N Attr VioWrt N Cell<br>VioWrt N Char VioWrt TTY VioScr Lock VioPop Up          |
| Tools      | BIND  |
| Modules    | DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL   |
| Libraries  | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB   |

2018/08/25 15:05 · prokushev · 0 Comments

From:  
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:  
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:vioreadcellstr>

Last update: 2021/09/19 02:21