



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

VioScrollRt

This call scrolls the entire display buffer (or area specified within the display buffer) to the right.

Syntax

```
VioScrollRt (TopRow, LeftCol, BotRow, RightCol, Lines, Cell, VioHandle)
```

Parameters

- TopRow ([USHORT](#)) - input : Top row to be scrolled.
- LeftCol ([USHORT](#)) - input : Left column to be scrolled.
- BotRow ([USHORT](#)) - input : Bottom row to be scrolled.
- RightCol ([USHORT](#)) - input : Right column to be scrolled.
- Lines ([USHORT](#)) - input : Number of columns to be inserted at the left of the screen area being scrolled. If 0 is specified, no lines are scrolled.
- Cell ([PBYTE](#)) - input : Address of the character attribute(s) pair (2 or 4 bytes) used as a fill character on inserted columns.
- VioHandle ([HVIO](#)) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

Return Code

rc ([USHORT](#)) - return

Return code descriptions are:

- 0 NO_ERROR
- 355 ERROR_VIO_MODE
- 358 ERROR_VIO_ROW
- 359 ERROR_VIO_COL
- 436 ERROR_VIO_INVALID_HANDLE
- 465 ERROR_VIO_DETACHED

Remarks

TopRow = 0 and LeftCol = 0 identifies the top left corner of the screen.

If a value greater than the maximum value is specified for TopRow, LeftCol, BotRow, RightCol, or Lines, the maximum value for that parameter is used.

If TopRow and LeftCol = 0 and if BotRow, RightCol, and Lines = 65535 (or -1 in assembler language), the entire screen is filled with the character-attribute pair defined by Cell.

Bindings

C Binding

```
#define INCL_VIO

USHORT rc = VioScrollRt(TopRow, LeftCol, BotRow, RightCol, Lines, Cell,
VioHandle);

USHORT          TopRow;           /* Top row */
USHORT          LeftCol;          /* Left column */
USHORT          BotRow;           /* Bottom row */
USHORT          RightCol;         /* Right column */
USHORT          Lines;            /* Number of lines */
PBYTE           Cell;             /* Cell to be written */
HVI0            VioHandle;        /* Video handle */

USHORT          rc;               /* return code */
```

MASM Binding

```
EXTRN VioScrollRt:FAR
INCL_VIO      EQU 1

PUSH WORD    TopRow      ;Top row
PUSH WORD    LeftCol     ;Left column
PUSH WORD    BotRow      ;Bottom row
PUSH WORD    RightCol    ;Right column
PUSH WORD    Lines       ;Number of lines
PUSH@ OTHER  Cell        ;Cell to be written
PUSH WORD    VioHandle   ;Video handle
CALL VioScrollRt
```

Returns WORD

Note

Text based on <http://www.edm2.com/index.php/VioScrollRt>

Family API	
DOS	Process Manager DosBeep DosExit DosSleep DosExecPgm
	File Manager DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time DosSet DateTime DosGet DateTime
	Devices DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals DosHold Signal DosSet Sig Handler
	Misc BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD	KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO	VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt VioScr Un Lock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf VioWrt Cell Str VioWrt Char Str VioWrt Char Str Att VioWrt N Attr VioWrt N Cell VioWrt N Char VioWrt TTY VioScr Lock VioPop Up
Tools	BIND
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://osfree.org/doku/> - osFree wiki



Permanent link:
<http://osfree.org/doku/doku.php?id=en:docs:fapi:vioscrollrt>

Last update: **2021/09/19 02:54**