



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

VioSetCp

This call allows a process to set the code page used to display text data on the screen for the specified handle.

Syntax

```
VioSetCp (Reserved, CodePageID, VioHandle)
```

Parameters

- Reserved (USHORT) - input: Reserved word of 0s.
- CodePageID (USHORT) - input: The CodePageID must be either 0, -1, -2, or have been specified on the CONFIG.SYS CODEPAGE = statement. A value of 0000 indicates that the code page is to be set to the default ROM code page provided by the hardware. A value of -1 enables the user font codepage if user fonts have previously been set with [VioSetFont](#). A value of -2 disables the user font and re-enables the prepared system codepage or ROM codepage that was active before the user font was enabled.

If the code page ID is not 0, -1, -2, or does not match one of the ID's on the CODEPAGE = statement, an error results. Refer to IBM Operating System/2 Command Reference for a complete description of CODEPAGE.

- VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by [VioGetPs](#).

Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO_ERROR
- 355 ERROR_VIO_MODE
- 436 ERROR_VIO_INVALID_HANDLE
- 465 ERROR_VIO_DETACHED
- 469 ERROR_VIO_BAD_CP

- 470 ERROR_VIO_NO_CP
- 471 ERROR_VIO_NA_CP

Remarks

VioSetCp can be used to enable and disable the user font code page as well as the prepared system code pages. If a prepared system code page or the ROM code page is specified, any previously set code page is disabled and the specified code page is enabled.

Specifying the special code page of -1 enables the user font code page if user fonts have previously been set. Specifying the special code page of -2 disables the user font code page and re-enables the prepared system code page or ROM code page that was active before the user font code page was enabled.

PM Considerations

Valid CodePageID values are 0 or one that was specified on the CONFIG.SYS

CODEPAGE = statement; -1 and -2 are not valid for PM.

This call can be used to set an **EBCDIC** code page for Advanced VIO. For a full-screen or Vio-windowed application, this function causes the displayed characters to be reinterpreted immediately in the new code page. For a Presentation Manager application, the characters in the base font are reinterpreted in the new code page only when other events cause the characters to be repainted. This function has no effect on displayed characters that use a font other than the base font.

Bindings

C

```
#define INCL_VIO

USHORT rc = VioSetCp(Reserved, CodePageID, VioHandle);

USHORT Reserved;      /* Reserved (must be zero) */
USHORT CodePageID;    /* CodePage Id */
HVI0   VioHandle;     /* Video handle */

USHORT rc;            /* return code */
```

MASM

```
EXTRN VioSetCp:FAR
INCL_VIO EQU 1
```

```
PUSH WORD Reserved ;Reserved (must be zero)
PUSH WORD CodePageID ;CodePage Id
PUSH WORD VioHandle ;Video handle
CALL VioSetCp
```

Returns WORD

Family API

	Process Manager	DosBeep DosExit DosSleep DosExecPgm
DOS	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreateCS Alias
	NLS	DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time	DosSet Date Time DosGet Date Time
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSet Sig Handler
	Misc	BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD		KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO		VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt VioScr Un Lock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf VioWrt Cell Str VioWrt Char Str VioWrt Char Att VioWrt N Attr VioWrt N Cell VioWrt N Char VioWrt TTY VioScr Lock VioPop Up
Tools		BIND
Modules		DOSCALS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://ftp.osfree.org/doku/> - osFree wiki

Permanent link:
<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:viosetcp>

Last update: 2021/11/04 12:44

