# Int 21H, AH=00H

## Version

1 and higher

## Brief

TERMINATE PROGRAM

## Family API

DosExit

## Input

```
AH = 00h
CS = PSP segment
```

## Return

never returns

## Notes

Microsoft recommends using INT 21/AH=4Ch for DOS 2+. This function sets the program's return code (ERRORLEVEL) to 00h. Execution continues at the address stored in INT 22 after DOS performs whatever cleanup it needs to do (restoring the INT 22,INT 23,INT 24 vectors from the PSP assumed to be located at offset 0000h in the segment indicated by the stack copy of CS, etc.). If the PSP is its own parent, the process's memory is not freed; if INT 22 additionally points into the terminating program, the process is effectively NOT terminated. Not supported by MS Windows 3.0 DOSX.EXE DOS extender

# See also

AH=4Ch,AH=26h,AH=31h, INT 20

# Note

Text based on Ralf Brown Interrupt List Release 61

| **DOS API** | |
|---|---|
| Process manager | INT 20H, **INT 21H**: 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H |
| File manager | INT 25H, INT 26H, **INT 21H**: 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O | INT 29H, **INT 21H**: 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH |
| Signals | INT 23H, INT 24H, **INT 21H**: 3300H, 3301H, 3302H |
| Memory manager | **INT 21H**: 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H |
| Date and Time | **INT 21H**: 2AH, 2BH, 2CH, 2DH |
| Misc | **INT 21H**: 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H |
| NLS | **INT 21H**: 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H |
| Devices | **INT 21H**: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H |
| Network | **INT 21H**: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H |
| **osFree Macro Library** | |
| Video I/O | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info | @Equipment @MemSize |
| Serial I/O | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus |
| Tape I/O | @TapeOn @TapeOff @TapeRead @TapeWrite |
| Keyboard I/O | @KbdStatus @CharIn @CharPeek |
| Printer I/O | @PrnPrint @PrnInit @PrnStatus |
| Disk I/O | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat |
| Date and Time | @SetTime @GetTime |
| Mouse | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion |
| Memory manager | @ModBlok SET_BLOCK |

2022/10/04 14:28 · prokushev · 0 Comments
2018/09/04 17:23 · prokushev · 0 Comments

| **Family API** | | |
|---|---|---|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOCtl DosDevIOCtl2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| KBD | | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |
| VIO | | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| Tools | | BIND |
| Modules | | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL |
| Libraries | | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · prokushev · 0 Comments

From:
http://185.82.219.184/doku/ - **osFree wiki**

Permanent link:
**http://185.82.219.184/doku/doku.php?id=en:docs:dos:api:int21:00&rev=1536120123**

Last update: **2018/09/05 04:02**