



Note: This IBM PC BIOS API call is for DOS/Win16 personality only. Use [Family API](#) for portability.

Note: [osFree Macro Library](#) provides macros for most of functions

2022/03/13 05:41 · prokushev · [0 Comments](#)

Int 1AH, AH=00H

Version

IBM 5150 and higher

Brief

GetTime

Family API

[DosGetDateTime](#)

Input

- AH = 00h

Return

- CX:DX = number of clock ticks since midnight
- AL = midnight flag, nonzero if midnight passed since time last read

Macro

```
INCLUDE BIOS.INC
```

```
@GetTime
```

Notes

- there are approximately 18.2 clock ticks per second, 1800B0h per 24 hrs (except on Tandy 2000, where the clock runs at 20 ticks per second)
- IBM and many clone BIOSes set the flag for AL rather than incrementing it, leading to loss of a day if two consecutive midnights pass without a request for the time (e.g. if the system is on but idle)
- since the midnight flag is cleared, if an application calls this function after midnight before DOS does, DOS will not receive the midnight flag and will fail to advance the date
- Modern releases of MS-DOS/PC DOS (5.0+???) assume that AL is a day rollover counter rather than a flag, as expected by older releases. DOS 5 - 7.10 (Windows 98 SE) provide an undocumented CONFIG.SYS SWITCHES=/T option to force the old behaviour of the day advancing code, that is using a flag instead of a counter.
- DR DOS 3.31 - DR-DOS 7.03 handle AL as a flag.

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

IBM PC BIOS API	
Video I/O	INT 10H : 00H , 01H , 02H , 03H , 05H , 06H , 07H , 08H , 09H , 0AH , 0BH , 0CH , 0DH , 0EH , 0FH
Hardware info	INT 11H , INT 12H
Serial I/O	INT 14H : 00H , 01H , 02H , 03H
Tape I/O	INT 15H : 00H , 01H , 02H , 03H
Keyboard I/O	INT 16H : 00H , 01H , 02H
Printer I/O	INT 17H : 00H , 01H , 02H
Disk I/O	INT 13H : 00H , 01H , 02H , 03H , 04H , 05H
Date and Time	INT 1AH : 00H , 01H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @CIs
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · [prokushev](#) · [0 Comments](#)

2022/03/13 05:54 · [prokushev](#) · [0 Comments](#)

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDSCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://www.osfree.ru/doku/> - **osFree wiki**

Permanent link:
<https://www.osfree.ru/doku/doku.php?id=en:docs:bios:api:int1a:00>

Last update: **2022/03/26 16:00**

