



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 23H

Version

1 and higher

Brief

CONTROL-C/CONTROL-BREAK HANDLER

Family API

Input

none

Return

1. -DOS 1.x—

AH = 00h abort program

```
if all registers preserved, restart DOS call
---DOS 2+---
CF clear
    all registers preserved
return via RETF with CF set or (MS-DOS 1,DR DOS) RETF 2 with CF set
    DOS will abort program with errorlevel 0
else (RETF/RETF 2 with CF clear or IRET with CF ignored)
    interrupted DOS call is restarted
```

Macro

Notes

this interrupt is invoked whenever DOS detects a ^C or ^Break; it should never be called directly
 MS-DOS 1.25 also invokes INT 23 on a divide overflow (INT 00)
 MS-DOS remembers the stack pointer before calling INT 23, and if it is not the same on return, pops and discards the top word; this is what permits a return with RETF as well as IRET or RETF 2
 MS-DOS 2.1+ ignores the returned CF if SP is the same on return as it was when DOS called INT 23, so RETF 2 will not terminate the program
 Novell DOS 7 always pops a word if CF is set on return, so one should not return with RETF 2 and CF set or IRET with the stored flags' CF set
 any DOS call may safely be made within the INT 23 handler, although the handler must check for a recursive invocation if it does call DOS

See Also

[INT 1B, INT 21/AH=92h"PTS-DOS"](#)

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H , INT 21H : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H , INT 27H , INT 28H
File manager	INT 25H , INT 26H , INT 21H : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H , INT 21H : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H , INT 24H , INT 21H : 3300H, 3301H, 3302H
Memory manager	INT 21H : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	INT 21H : 2AH, 2BH, 2CH, 2DH
Misc	INT 21H : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	INT 21H : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H

DOS API	
Devices	INT 21H: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	INT 21H: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAIInfo @ClS
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushhev · 0 Comments

2018/09/04 17:23 · prokushhev · 0 Comments

Family API	
DOS	Process Manager DosBeep DosExit DosSleep DosExecPgm
	File Manager DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHand State DosNewSize DosBufReset DosQFHand State DosSet FSinfo
	Memory Manager DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreateCS Alias
	NLS DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time DosSetDateTime DosGetDateTime
	Devices DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals DosHoldSignal DosSetSigHandler
	Misc BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools	BIND
Modules	DOSCALS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushhev · 0 Comments

From:
<http://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<http://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int23>

Last update: **2021/08/06 07:19**