



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

MouGetScaleFact

This call returns a pair of 1-word scaling factors for the current mouse device.

Syntax

MouGetScaleFact (ScaleStruct, DeviceHandle)

Parameters

- ScaleStruct (PSCALEFACT) - output: Address of the control block structure that contains the current row and column coordinate scaling factors.

See [MouSetScaleFact](#) for more information.

- DeviceHandle (HMOU) - input: Contains the handle of the mouse device obtained from a previous MouOpen.

Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO_ERROR
- 385 ERROR_MOUSE_NO_DEVICE
- 466 ERROR_MOU_DETACHED
- 501 ERROR_MOUSE_NO_CONSOLE
- 505 ERROR_MOU_EXTENDED_SG

Remarks

The units of the scale factor depend on the mode of the display screen for the session. If the screen is operating in text mode, the scaling units are relative to characters. If the screen is operating in graphics mode, the scaling units are relative to pels.

Bindings

C

```

typedef struct _SCALEFACT { /* mousc */
    USHORT rowScale;           /* row scaling factor */
    USHORT colScale;          /* column coordinate scaling factor */
} SCALEFACT;

#define INCL_MOU

USHORT rc = MouGetScaleFact(ScaleStruct, DeviceHandle);

PSCALEFACT ScaleStruct; /* 2-word structure */
HMOU     DeviceHandle; /* Mouse device handle */

USHORT rc;             /* return code */

```

MASM

```

SCALEFACT struc
    mousc_rowScale dw ? ;row scaling factor
    mousc_colScale dw ? ;column coordinate scaling factor
SCALEFACT ends

EXTRN MouGetScaleFact:FAR
INCL_MOU EQU 1

PUSH@ OTHER ScaleStruct ;2-word structure
PUSH WORD DeviceHandle ;Mouse device handle
CALL MouGetScaleFact

Returns WORD

```

Family API	
DOS	Process Manager DosBeep DosExit DosSleep DosExecPgm
	File Manager DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time DosSet Date Time DosGet Date Time
	Devices DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals DosHoldSignal DosSet Sig Handler
	Misc BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD	KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO	VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt VioScr Un Lock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf VioWrt Cell Str VioWrt Char Str VioWrt Char Str Att VioWrt N Attr VioWrt N Cell VioWrt N Char VioWrt TTY VioScr Lock VioPop Up
Tools	BIND
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:mougetscalefact>

Last update: **2021/11/04 13:13**