



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

DosDevConfig

This call gets information about attached devices.

Syntax

```
DosDevConfig (DeviceInfo, Item, Parm)
```

Parameters

- DeviceInfo ([PVOID](#)) - output: Address of the byte-wide field containing the requested information.
- Item ([USHORT](#)) - input: Device information requested.
 - 0 - Number of printers attached
 - 1 - Number of RS232 ports
 - 2 - Number of diskette drives
 - 3 - Presence of math coprocessor (where 0 = not present, 1 = present)
 - 4 - PC Submodel Type (where the return is the system submodel byte)
 - 5 - PC Model Type (where the return is the system model byte)
 - 6 - Display adapter type (where 0 = monochrome mode compatible, 1 = other).
- Parm ([USHORT](#)) - input: Reserved for future use and should be set to zero.

Return Code

rc ([USHORT](#)) - return: Return code descriptions are:

- 0 NO_ERROR
- 87 ERROR_INVALID_PARAMETER

Remarks

The system model (function 5) and submodel (function 4) information is obtained from BIOS.

In addition, the number of devices attached in a PS/2 environment reflect only devices that are “awake”. Devices that are “asleep” are not counted.

Bindings

C

```
#define INCL_DOSDEVICES

USHORT rc = DosDevConfig(DeviceInfo, Item, Parm);

PVOID DeviceInfo;      /* Returned information */
USHORT Item;           /* Item number */
USHORT Parm;           /* Reserved */

USHORT rc;              /* return */
```

MASM

```
EXTRN DosDevConfig:FAR
INCL_DOSDEVICES EQU 1

PUSH@ OTHER DeviceInfo ;Requested information (returned)
PUSH WORD Item ;Item number
PUSH WORD Parm ;Reserved (must be zero)
CALL DosDevConfig
```

Returns WORD

Example Code

This example gets information about model type, monitor and coprocessor and display it.

```
#define INCL_DOSDEVICES

#define MACHINE_MODEL 5
#define DISPLAY_TYPE 6
#define FIND_COPROCESSOR 3
#define RESERVED 0L

BYTE DeviceInfo;
USHORT rc;

if(!DosDevConfig(&DeviceInfo, MACHINE_MODEL, RESERVED))
```

/* Returned information */
 /* Item number */
 /* Reserved */

```

        printf("Model Type %d ",DeviceInfo);

    if(!DosDevConfig(&DeviceInfo,
                     DISPLAY_TYPE,
                     RESERVED))           /* Returned information */
                                /* Item number */
                                /* Reserved */

        if (DeviceInfo)
            printf("Colour display ");
        else
            printf("Mono display ");

    if(!DosDevConfig(&DeviceInfo,
                     FIND_COPROCESSOR,
                     RESERVED))          /* Returned information */
                                /* Item number */
                                /* Reserved */

        if (DeviceInfo)
            printf("Coprocessor");
        else
            printf("No Coprocessor");

```

Note

Text based on [http://www.edm2.com/index.php/DosDevConfig_\(Legacy\)](http://www.edm2.com/index.php/DosDevConfig_(Legacy))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHand State DosNewSize DosBufReset DosQFHand State DosSet FSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS	DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time	DosSet Date Time DosGet Date Time
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSet Sig Handler
	Misc	BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD		KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO		VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str Vio Scroll Up Vio Scroll Dn Vio Scroll If Vio Scroll Rt Vio Scr Un Lock Vio Set Cur Pos Vio Set Cur Type Vio Set Mode Vio Get Mode Vio Show Buf Vio Wrt Cell Str Vio Wrt Char Str Vio Wrt Char Str Att Vio Wrt N Attr Vio Wrt N Cell Vio Wrt N Char Vio Wrt TTY Vio Scr Lock Vio Pop Up
Tools		BIND
Modules		DOSCALLS.DLL VIOCALS.DLL KBDCALS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:
<http://www.osfree.org/doku/> - osFree wiki



Permanent link:
<http://www.osfree.org/doku/doku.php?id=en:docs:fapi:dosdevconfig>

Last update: **2021/09/17 04:58**