



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## MouSetPtrShape

This call allows a process to set the pointer shape and size to be used as the mouse device driver pointer image for all applications in a session.

### Syntax

```
MouSetPtrShape (PtrBuffer, PtrDefRec, DeviceHandle)
```

### Parameters

- **PtrBuffer** (PBYTE) - input: Address of a buffer containing the bit image used by the mouse device driver as the pointer shape for that session. The buffer consists of AND and XOR pointer masks in a format meaningful to the pointer draw device driver.

For CGA compatible text modes (0, 1, 2, and 3) the following describes the AND and XOR pointer mask bit definitions for each character cell of the masks. Bit values are:

| Bit   | Description       |
|-------|-------------------|
| 15    | Blinking          |
| 14-12 | Background colour |
| 11    | Intensity         |
| 10-8  | Foreground colour |
| 7-0   | Character         |

- **PtrDefRec** (PPTRSHAPE) - input: Address of the structure where the application stores the necessary data for the pointer draw device driver to build a row-by-column image for each bit plane for the current display mode.

**Programming Note:** For other custom displays and for the extended modes of the EGA attachment, it is possible to set the display to modes that require multiple bit planes. In these cases, the area sized by the row and column limits must be repeated for each bit plane supported in that mode. Consequently, the calling process must supply enough data to allow the mouse device driver to draw the pointer shape on all currently supported bit planes in that session. For text modes, row and column offset must equal 0.

- DeviceHandle (HMOU) - input: Contains the handle of the mouse device obtained from a previous MouOpen.

## Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO\_ERROR
- 385 ERROR\_MOUSE\_NO\_DEVICE
- 387 ERROR\_MOUSE\_INV\_PARMS
- 466 ERROR\_MOU\_DETACHED
- 501 ERROR\_MOUSE\_NO\_CONSOLE
- 505 ERROR\_MOU\_EXTENDED\_SG

## Remarks

An application passes a data image to the mouse device driver that the mouse driver applies to the screen whenever the logical pointer position is not located in the application-defined collision area. The application synchronizes use of the screen with the mouse driver by way of MouRemovePtr and MouDrawPtr.

The pointer shape is dependent on the display device driver used to support the display device. OS/2 supports text and graphics modes. These modes are restricted to modes 0 through 7, depending on the display device. Character modes (modes 0, 1, 2, 3, and 7) support the pointer cursor only as a reverse block character. This reverse block character has a character height and width equal to 1.

The pointer shape is mapped by the Pointer Draw Device Driver and determined completely by the application. The height and width may vary from 1 through the pel size of the display screen. For restrictions concerning the Pointer Draw Device Driver, see IBM Operating System/2 Version 1.2 I/O Subsystems And Device Support Volume 1.

## Bindings

### C

```
typedef struct _PTRSHAPE { /* moups */
    USHORT cb;           /* total length necessary to build image */
    USHORT col;          /* # of columns in mouse shape */
    USHORT row;          /* number of rows in mouse shape */
    USHORT colHot;       /* column coordinate of pointer image hotspot */
    USHORT rowHot;       /* row coordinate of pointer image hotspot */
} PTRSHAPE;

#define INCL_MOU

USHORT rc = MouSetPtrShape(PtrBuffer, PtrDefRec, DeviceHandle);
```

```
PBYTE      PtrBuffer;      /* Pointer shape buffer */
PPTRSHAPE  PtrDefRec;     /* Pointer definition record */
HMOU       DeviceHandle;  /* Mouse device handle */

USHORT     rc;            /* return code */
```

## MASM

```
PTRSHAPE struct
  mousps_cb      dw  ? ;total length necessary to build image
  mousps_col     dw  ? ;# of columns in mouse shape
  mousps_row     dw  ? ;number of rows in mouse shape
  mousps_colHot  dw  ? ;column coordinate of pointer image hotspot
  mousps_rowHot  dw  ? ;row coordinate of pointer image hotspot
PTRSHAPE ends
```

```
EXTRN MouSetPtrShape:FAR
INCL_MOU      EQU 1
```

```
PUSH@ OTHER  PtrBuffer      ;Pointer shape buffer
PUSH@ OTHER  PtrDefRec     ;Pointer definition record
PUSH WORD    DeviceHandle  ;Mouse device handle
CALL        MouSetPtrShape
```

Returns **WORD**

| Family API |                 |  |
|------------|-----------------|--|
| DOS        | Process Manager | DosBeep DosExit DosSleep DosExecPgm  |
|            | File Manager    | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove<br>DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead<br>DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose<br>DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks<br>DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo |
|            | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAllocSeg<br>DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreateCSAlias   |
|            | NLS             | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate<br>DosGetMessage DosInsMessage DosPutMessage   |
|            | Date and Time   | DosSetDateTime DosGetDateTime  |
|            | Devices         | DosDevConfig DosDevIOCtl DosDevIOCtl2  |
|            | Signals         | DosHoldSignal DosSetSigHandler   |
|            | Misc            | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass<br>DosSetVec   |
| KBD        |                 | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek   |

| <b>Family API</b> |   |
|-------------------|---|
| VIO               | <a href="#">VioGetBuf</a> <a href="#">VioGetConfig</a> <a href="#">VioGetCurPos</a> <a href="#">VioGetCurType</a> <a href="#">VioGetPhysBuf</a><br><a href="#">VioReadCellStr</a> <a href="#">VioReadCharStr</a> <a href="#">VioScrollUp</a> <a href="#">VioScrollDn</a> <a href="#">VioScrollLf</a> <a href="#">VioScrollRt</a><br><a href="#">VioScrUnLock</a> <a href="#">VioSetCurPos</a> <a href="#">VioSetCurType</a> <a href="#">VioSetMode</a> <a href="#">VioGetMode</a> <a href="#">VioShowBuf</a><br><a href="#">VioWrtCellStr</a> <a href="#">VioWrtCharStr</a> <a href="#">VioWrtCharStrAtt</a> <a href="#">VioWrtNAttr</a> <a href="#">VioWrtNCell</a><br><a href="#">VioWrtNChar</a> <a href="#">VioWrtTTY</a> <a href="#">VioScrLock</a> <a href="#">VioPopUp</a> |
| Tools             | BIND  |
| Modules           | <a href="#">DOSCALLS.DLL</a> <a href="#">VIOCALLS.DLL</a> <a href="#">KBDCALLS.DLL</a> <a href="#">MSG.DLL</a>  |
| Libraries         | <a href="#">API.LIB</a> <a href="#">OS2386.LIB</a> <a href="#">FAPI.LIB</a> <a href="#">DOSCALLS.LIB</a> <a href="#">SUBCALLS.LIB</a>   |

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:  
<http://ftp.osfree.org/doku/> - **osFree wiki**



Permanent link:  
<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:mouseptrshape>

Last update: **2021/11/04 13:11**