

TPCrt

FrameWindow

```
procedure FrameWindow(LeftCol, TopRow, RightCol, BotRow, FAttr, HAttr :  
Byte; Header : shortstring);
```

Draw a frame around a window

WhereXAbs

```
function WhereXAbs: Byte;
```

Return absolute column coordinate of cursor

WhereYAbs

```
function WhereYAbs: Byte;
```

Return absolute row coordinate of cursor

WhereXY

```
function WhereXY: Word;
```

Return absolute coordinates of cursor

ScreenX

```
function ScreenX: Byte;
```

Return absolute column coordinate of cursor

ScreenY

```
function ScreenY: Byte;
```

Return absolute row coordinate of cursor

FastWrite

```
procedure FastWrite(St : string; Row, Col, Attr : Byte);
```

Write St at Row,Col in Attr (video attribute) without snow

SetFrameChars

```
procedure SetFrameChars(Vertical, Horizontal, LowerRight, UpperRight,  
LowerLeft, UpperLeft : Char);
```

Sets the frame characters to be used on subsequent FrameWindow calls.

WhereXYdirect

```
procedure WhereXYdirect(var X, Y : Byte);
```

Read the current position of the cursor directly from the CRT controller

GetCrtMode

```
function GetCrtMode : Byte;
```

Get the current video mode. Also reinitializes internal variables. May reset: CurrentMode, ScreenWidth, ScreenHeight, CurrentPage, and VideoSegment.

GotoXYAbs

```
procedure GotoXYAbs(X, Y : Byte);
```

Move cursor to column X, row Y. No error checking done.

SetVisiblePage

```
procedure SetVisiblePage(PageNum : Byte);
```

Set current video page

ScrollWindowUp

```
procedure ScrollWindowUp(XLo, YLo, XHi, YHi, Lines : Byte);
```

Scrolls the designated window up the specified number of lines.

ScrollWindowDown

```
procedure ScrollWindowDown(XLo, YLo, XHi, YHi, Lines : Byte);
```

Scrolls the designated window down the specified number of lines.

CursorTypeSL

```
function CursorTypeSL : Word;
```

Returns a word. High byte has starting scan line, low byte has ending.

```
function CursorStartLine : Byte;
```

```
{-Returns the starting scan line of the cursor}
```

```
function CursorEndLine : Byte;
```

```
{-Returns the ending scan line of the cursor.}
```

```
procedure SetCursorSize(Startline, EndLine : Byte);
```

```
{-Sets the cursor's starting and ending scan lines.}
```

```
procedure NormalCursor;
```

```
{-Set normal scan lines for cursor based on current video mode}
```

```
procedure FatCursor;
```

```
{-Set larger scan lines for cursor based on current video mode}
```

```
procedure BlockCursor;
```

```
{-Set scan lines for a block cursor}
```

```
procedure HiddenCursor;
```

```
{-Hide the cursor}
```

function ReadCharAtCursor : Char;

{-Returns character at the current cursor location on the selected page.}

function ReadAttrAtCursor : Byte;

{-Returns attribute at the current cursor location on the selected page.}

procedure GetCursorState(var XY, ScanLines : Word);

{-Return the current position and size of the cursor}

procedure RestoreCursorState(XY, ScanLines : Word);

{-Reset the cursor to a position and size saved with GetCursorState}

procedure FastWriteWindow(St : string; Row, Col, Attr : Byte);

{-Write a string using window-relative coordinates}

procedure FastText(St : string; Row, Col : Byte);

{-Write St at Row,Col without changing the underlying video attribute.}

procedure FastTextWindow(St : string; Row, Col : Byte);

{-Write St at window Row,Col without changing the underlying video attribute.}

procedure FastVert(St : string; Row, Col, Attr : Byte);

{-Write St vertically at Row,Col in Attr (video attribute)}

procedure FastVertWindow(St : string; Row, Col, Attr : Byte);

{-Write a string vertically using window-relative coordinates}

procedure FastFill(Number : Word; Ch : Char; Row, Col, Attr : Byte);

{-Fill Number chs at Row,Col in Attr (video attribute) without snow}

procedure FastFillWindow(Number : Word; Ch : Char; Row, Col, Attr : Byte);

{-Fill Number chs at window Row,Col in Attr (video attribute) without snow}

procedure FastCenter(St : string; Row, Attr : Byte);

{-Write St centered on window Row in Attr (video attribute) without snow}

procedure FastFlush(St : string; Row, Attr : Byte);

```
{-Write St flush right on window Row in Attr (video attribute) without snow}
```

procedure FastRead(Number, Row, Col : Byte; var St : string);

```
{-Read Number characters from the screen into St starting at Row,Col}
```

procedure FastReadWindow(Number, Row, Col : Byte; var St : string);

```
{-Read Number characters from the screen into St starting at window Row,Col}
```

procedure ReadAttribute(Number, Row, Col : Byte; var St : string);

```
{-Read Number attributes from the screen into St starting at Row,Col}
```

procedure ReadAttributeWindow(Number, Row, Col : Byte; var St : string);

```
{-Read Number attributes from the screen into St starting at window Row,Col}
```

procedure WriteAttribute(St : String; Row, Col : Byte);

```
{-Write string of attributes St at Row,Col without changing characters}
```

procedure WriteAttributeWindow(St : String; Row, Col : Byte);

```
{-Write string of attributes St at window Row,Col without changing characters}
```

procedure ChangeAttribute(Number : Word; Row, Col, Attr : Byte);

```
{-Change Number video attributes to Attr starting at Row,Col}
```

procedure ChangeAttributeWindow(Number : Word; Row, Col, Attr : Byte);

```
{-Change Number video attributes to Attr starting at window Row,Col}
```

procedure MoveScreen(var Source, Dest; Length : Word);

```
{-Move Length words from Source to Dest without snow}
```

procedure FlexWrite(St : string; Row, Col : Byte; var FAttrs : FlexAttrs);

```
{-Write St at Row,Col with flexible color handling}
```

procedure FlexWriteWindow(St : string; Row, Col : Byte; var FAttrs : FlexAttrs);

```
{-Write a string flexibly using window-relative coordinates.}
```

```
function SaveWindow(XLow, YLow, XHigh, YHigh : Byte; Allocate : Boolean;
```

```
    var Covers : Pointer) : Boolean;
{-Allocate buffer space if requested and save window contents}
```

```
procedure RestoreWindow(XLow, YLow, XHigh, YHigh : Byte;
```

```
    Deallocate : Boolean; var Covers : Pointer);
{-Restore screen contents and deallocate buffer space if requested}
```

```
procedure StoreWindowCoordinates(var WC : WindowCoordinates);
```

```
{-Store the window coordinates for the active window}
```

```
procedure RestoreWindowCoordinates(WC : WindowCoordinates);
```

```
{-Restore previously saved window coordinates}
```

```
function PackWindow(XLow, YLow, XHigh, YHigh : Byte) : PackedWindowPtr;
```

```
{-Return a pointer to a packed window, or nil if not enough memory}
```

```
procedure DispPackedWindow(PWP : PackedWindowPtr);
```

```
{-Display the packed window pointed to by PWP}
```

```
procedure DispPackedWindowAt(PWP : PackedWindowPtr; Row, Col : Byte);
```

```
{-Display the packed window pointed to by PWP at Row,Col. If necessary,
the coordinates are adjusted to allow it to fit on the screen.}
```

```
procedure MapPackedWindowColors(PWP : PackedWindowPtr);
```

```
{-Map the colors in a packed window for improved appearance on mono/B&W
displays}
```

```
procedure DisposePackedWindow(var PWP : PackedWindowPtr);
```

```
{-Dispose of a packed window, setting PWP to nil on exit}
```

```
procedure WritePackedWindow(PWP : PackedWindowPtr; FName : string);
```

```
{-Store the packed window pointed to by PWP in FName}
```

```
function ReadPackedWindow(FName : string) : PackedWindowPtr;
```

```
{-Read the packed window stored in FName into memory}
```

```
function CreateLibrary(var F : file; Name : string;
```

```
        Entries : Byte) : DirectoryPtr;  
{-Create a library with the specified # of directory entries}
```

```
function OpenLibrary(var F : file; Name : string) : DirectoryPtr;
```

```
{-Open the specified library and return a pointer to its directory}
```

```
procedure CloseLibrary(var F : file; var DP : DirectoryPtr);
```

```
{-Close library F and deallocate its directory}
```

```
procedure PackLibrary(LName : string);
```

```
{-Pack a library to remove deleted entries.}
```

```
procedure AddWindowToLibrary(PWP : PackedWindowPtr; var F : file;
```

```
        DP : DirectoryPtr; WinName : LibName);  
{-Add a packed window to the specified library}
```

```
function ReadWindowFromLibrary(var F : file; DP : DirectoryPtr;
```

```
        WinName : LibName) : PackedWindowPtr;  
{-Read a packed window from a library}
```

```
procedure DeleteWindowFromLibrary(var F : file; DP : DirectoryPtr;
```

```
        WinName : LibName);  
{-Delete a packed window from the specified library}
```

```
function MapColor(c : Byte) : Byte;
```

```
{-Map a video attribute for visibility on mono/bw displays}
```

```
procedure SetBlink(Status : Boolean);
```

```
{-Enable text mode attribute blinking if On is True}
```

```
procedure SetCrtBorder(Attr : Byte);
```

```
{-Set border to background color if card type and mode allow}
```

```
function Font8x8Selected : Boolean;
```

```
{-Return True if EGA or VGA is active and in 8x8 font}
```

```
procedure SelectFont8x8(Status : Boolean);
```

```
{-Toggle 8x8 font on or off}
```

function HercPresent : Boolean;

```
{-Return true if a Hercules graphics card is present}
```

procedure SwitchInColorCard(ColorOn : Boolean);

```
{-Activate or deactivate colors on a Hercules InColor card}
```

function HercGraphicsMode : Boolean;

```
{-Return True if a Hercules card is in graphics mode}
```

function HercModeTestWorks : Boolean;

```
{-Return True if HercGraphicsMode will work}
```

procedure SetHercMode(GraphMode : Boolean; GraphPage : Byte);

```
{-Set Hercules card to graphics mode or text mode, and activate specified graphics page (if switching to graphics mode).}
```

function ReadKeyWord : Word;

```
{-Waits for keypress, then returns scan and character codes together}
```

function CheckKbd(var KeyCode : Word) : Boolean;

```
{-Returns True (and the key codes) if a keystroke is waiting}
```

function KbdFlags : Byte;

```
{-Returns keyboard status flags as a bit-coded byte}
```

procedure StuffKey(W : Word);

```
{-Stuff one key into the keyboard buffer}
```

procedure StuffString(S : string);

```
{-Stuff the contents of S into the keyboard buffer}
```

procedure RelnitCrt;

```
{-Reinitialize CRT unit's internal variables. For TSR's or programs with DOS shells. May reset: CurrentMode, ScreenWidth, ScreenHeight, WindMin/WindMax, CurrentPage, CurrentDisplay, CheckSnow, and VideoSegment}
```

```
{ifdef WIN32} procedure SetSafeCPSwitching(F: Boolean); procedure SetUseACP(F: Boolean);  
{endif}
```

procedure AssignConToCrt;

procedure ClrScr;

```
{-Clears the screen and returns the cursor to the upper-left corner}
```

procedure TextBackground(Color: Byte);

```
{-Selects the background color}
```

procedure TextColor(Color: Byte);

```
{-Selects the foreground character color}
```

procedure Window(X1,Y1,X2,Y2: Byte);

```
{-Defines a text window on the screen}
```

procedure GotoXY(X,Y: Byte);

```
{-Moves the cursor to the given coordinates within the screen}
```

function WhereX: Byte;

```
{-Returns the X coordinate of the current cursor location}
```

function WhereY: Byte;

```
{-Returns the Y coordinate of the current cursor location}
```

procedure ClrEol;

```
{-Clears all characters from the cursor position to the end of the line }  
{ without moving the cursor. }
```

function KeyPressed: Boolean;

```
{-Determines if a key has been pressed on the keyboard and returns True }  
{ if a key has been pressed }
```

function ReadKey: Char;

```
{-Reads a character from the keyboard and returns a character or an }  
{ extended scan code. }
```

procedure TextMode (Mode: word); procedure InsLine;

```
{-Inserts an empty line at the cursor position}
```

procedure DelLine;

```
{-Deletes the line containing the cursor}
```

```
procedure LowVideo;
```

```
{-Selects low intensity characters}
```

```
procedure HighVideo;
```

```
{-Selects high-intensity characters}
```

```
procedure NormVideo;
```

```
{-Selects normal intensity characters}
```

```
procedure Delay(MS: Word); procedure Sound(Hz: Word); procedure NoSound; procedure  
AssignCrt(var F: Text);
```

```
{-Associates a text file with CRT device.}
```

```
procedure PlaySound(Freq,Duration: Longint);
```

```
{-Setups window coordinates }
```

```
procedure GetLastMode;
```

From:

<http://185.82.219.184/doku/> - **osFree wiki**

Permanent link:

<http://185.82.219.184/doku/doku.php?id=en:docs:tpro&rev=1738993712>

Last update: **2025/02/08 05:48**

