Note: This IBM PC BIOS API call is for DOS/Win16 personality only. Use Family API for portability.

Note: osFree Macro Library provides macros for most of functions

2022/03/13 05:41 · prokushev · 0 Comments

@ScrollUp

Version

IBM 5150 and higher

Brief

Scroll Screen Area Up

BIOS Interrupt

INT10H: 06H

Family API

VioScrollUp

Syntax

```
@ScrollUp distance, atrib, upcol, uprow, downcol, downrow
```

Parameters

- distance (BYTE) - rows to scroll
- atrib (BYTE) - fill attribute
- upcol (BYTE) - upper left column
- uprow (BYTE) - upper left row
- downcol (BYTE) - down right column

- downrow (BYTE) - down right row

Return

IBM PC BIOS API	
Video I/O	**INT 10H**: 00H, 01H, 02H, 03H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0CH, 0DH, 0EH, 0FH
Hardware info	INT 11H, INT 12H
Serial I/O	**INT 14H**: 00H, 01H, 02H, 03H
Tape I/O	**INT 15H**: 00H, 01H, 02H, 03H
Keyboard I/O	**INT 16H**: 00H, 01H, 02H
Printer I/O	**INT 17H**: 00H, 01H, 02H
Disk I/O	**INT 13H**: 00H, 01H, 02H, 03H, 04H, 05H
Date and Time	**INT 1AH**: 00H, 01H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments
2022/03/13 05:54 · prokushev · 0 Comments

From:
http://ftp.osfree.org/doku/ - **osFree wiki**

Permanent link:
http://ftp.osfree.org/doku/doku.php?id=en:docs:macrolib:scrollup

Last update: **2022/10/08 03:26**