



ANSICALL

This is forwarder DLL to DOSCALLS.DLL. No any real code here.


Entry points


Ordinal	Type	Entry	Description	Status	FAPI	Version
1	16	AnsiInject	Inject ANSI Device Status Record output to KbdHandler buffer. Forwarder to DOSCALLS.848	Done	No	
2	16	AnsiKeydef	ANSI keyboard key reassignment. Forwarder to DOSCALLS.849	Done	No	
3	16	AnsiInterp	ANSI Control Code Sequence interpreter. Forwarder to DOSCALLS.850	Done	No	
11	32	Ansi32Inject	Inject ANSI Device Status Record output to KbdHandler buffer. Forwarder to DOSCALLS.		No	
12	32	Ansi32Keydef	ANSI keyboard key reassignment. Forwarder to DOSCALLS.		No	
13	32	Ansi32Interp	ANSI Control Code Sequence interpreter. Forwarder to DOSCALLS.		No	

Versions

Date&Time	SHA1	BldLevel/Version	Size	Comments
2011-09-17 06:13		14.100	463 bytes	By OSFree. Alternative Version. ANSI escape sequence API.
2002-03-08 19:16		N/A	512 bytes	By IBM
1992-02-06 16:52	36bdd7601ef3c615cabcae2e78db29220e774145	IBM Personal Computer DOS Version x.xx Protect Mode ANSI	3,339 bytes	IBM OS/2 SDK 1.3 CSD1
1988-08-08 00:00	6b761b46f4eaba4eafed58302be0c2ab6d565f83	IBM Personal Computer DOS Version x.xx Protect Mode ANSI	3,616 bytes	MS OS/2 SDK 1.05
1987-12-15 00:00	38a7c7b1bcf5f849fc9ac2408640ab9dce97d7	Microsoft OS/2 Version x.xx Protect Mode ANSI	3,637 bytes	MS OS/2 SDK 1.02
1987-10-21 00:00			?? bytes	MS OS/2 1.0

OS/2 DLLs	
Base API	DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS KBDSCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS BVSCALLS NAMPIPES QUECALLS OS2CHAR
Bidirectional NLS	BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM PMBIDI
Unicode API	UCONV UNIKBD LIBUNI
BVH (Base Video Handlers)	BVHINIT BVHMPA BVHVGGA BVHSVGA BVHWNDW
GRADD subsystem	VMAN SOFTDRAW GRE2VMAN GENGRADD
IPF (Information Presentation facility)	HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI ERRTXT
REXX	REXX REXXAPI REXXUTIL REGINA
The core PM DLL's	PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG PMCTLS PMMLE PMSPL PMVIOP PMWIN
Open32	PMWINX MIRRORS REGISTRY
Intelligent Font Interface drivers	PMATM TRUETYPE PMUNIF FREETYPE PMPRE
Data Exchange	PMCLIP PMDDE PMDDEML
VDM PM interface	PMVDMH PMVDMP SEAMLESS SHIELD
WPS	PMWP PMWPMRU PMVDDROP
Miscellaneous	PMPIC PMTKT MVDM
SOM API	SOM SOMC





2016/07/25 02:16 · prokushev · 0 Comments

OS/2 API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir dos16qcurdisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOctl
	Signals	DosHoldSignal DosSetSigHandler
	Misc	DosGetEnv DosGetMachineMode DosGetMessage DosGetVersion DosInsMessage DosPutMessage DosError DosErrClass DosSetVec
Keyboard Router		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek

OS/2 API		
Video Router		VioGetBuf VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioGetCP
Mouse Router		
Presentation Manager		
Workplace Shell		
REXX		
MMIO/2		
Tools		
Modules		Modules list
Libraries		DOSCALLS.LIB OS2.LIB PMMLE.LIB REXX.LIB RXSTRING.LIB OS2286.LIB OS2386.LIB PMBIND.LIB

2018/09/05 06:19 · prokushev · [0 Comments](#)

From:
<http://185.82.219.184/doku/> - **osFree wiki**

Permanent link:
<http://185.82.219.184/doku/doku.php?id=en:docs:os2:modules:ansicall&rev=1536326760>

Last update: **2018/09/07 13:26**

