



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

# DosSubFree

This call frees memory previously allocated by DosSubAlloc.

## Syntax

DosSubFree (SegSelector, BlockOffset, Size)

## Parameters

;SegSelector (SEL) - input : Data segment selector. ;BlockOffset (USHORT) - input : Memory block offset. The value specified must equal the BlockOffset returned on a previous DosSubAlloc call. ;Size (USHORT) - input : Size, in bytes, of the block to be freed.

## Return Code

rc (USHORT) - return Return code descriptions are: \* 0 NO\_ERROR \* 312 ERROR\_DOSSUB\_OVERLAP \* 313 ERROR\_DOSSUB\_BADSIZE

## Remarks

DosSubFree specifies the offset of a block of memory previously suballocated by a DosSubAlloc request. If the block specified overlaps memory in the segment that is not suballocated, an error is returned. Like DosSubAlloc, the size parameter must be a multiple of four bytes; otherwise, it is rounded up to a multiple of four bytes.

The allocated segment is freed by calling DosFreeSeg.

## Example Code

## C Binding

```
<PRE> #define INCL_DOSMEMMGR
```

```
USHORT rc = DosSubFree(SegSelector, BlockOffset, Size);
```

```
SEL SegSelector; /* Segment selector */ USHORT BlockOffset; /* Offset of memory block to free */  
USHORT Size; /* Size of block in bytes */
```

```
USHORT rc; /* return code */ </PRE>
```

## MASM Binding

```
<PRE> EXTRN DosSubFree:FAR INCL_DOSMEMMGR EQU 1
```

```
PUSH WORD SegSelector ;Segment selector PUSH WORD BlockOffset ;Offset of memory block to free  
PUSH WORD Size ;Size of block in bytes CALL DosSubFree
```

Returns WORD </PRE>

## Note

Text based on <http://www.edm2.com/index.php/DosSubFree>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGet Huge Shift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioSchrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND

**Family API**

Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:

<http://185.82.219.184/doku/> - osFree wiki

Permanent link:

<http://185.82.219.184/doku/doku.php?id=en:docs:fapi:dossubfree&rev=1629433890>Last update: **2021/08/20 04:31**