



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

KbdXlate

This call translates scan codes with shift states into ASCII codes.

Syntax

```
KbdXlate (XlataRecord, KbdHandle)
```

Parameters

- XlataRecord (PKBDTRANS) - input: Address of the translation record structure:
 - chardata (KBDKEYINFO): Character data information structure as defined in KbdCharIn call.
 - kbdflag (USHORT): See the KbdDDFlagWord call in the “Keyboard Device Driver” section of IBM Operating System/2 Version 1.2 I/O Subsystems And Device Support Volume 1.
 - xlate (USHORT): Translation flag:
 - 0 - Translation incomplete.
 - 1 - Translation complete.
 - xlatestate1 (USHORT): Identifies the state of translation across successive calls; initially the value should be zero. It may take several calls to this function to complete a character. The value should not be changed unless a new translation is required, that is, reset value to zero.
 - xlatestate2 (USHORT): See description for xlatestate1.
- KbdHandle (HKBD) - input: Default keyboard or the logical keyboard.

Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO_ERROR
- 439 ERROR_KBD_INVALID_HANDLE
- 445 ERROR_KBD_FOCUS_REQUIRED
- 447 ERROR_KBD_KEYBOARD_BUSY

- 464 ERROR_KBD_DETACHED
- 504 ERROR_KBD_EXTENDED_SG

Remarks

It may take several calls to complete a translation because of accent key combinations, or other complex operations.

The Xlatestate1 and Xlatestate2 are for use by the keyboard translation routines. These fields are reserved and must only be accessed by the caller prior to starting a translation sequence and then they must be set to zero. The KbdXlate function is intended to be used for translating a particular scan code for a given shift state. The KbdXlate function is not intended to be a replacement for the OS/2 system keystroke translation function.

Bindings

C

```
typedef struct _KBDTRANS { /* kbxl */
    UCHAR      chChar;      /* ASCII character code */
    UCHAR      chScan;     /* Scan code */
    UCHAR      fbStatus;   /* State of the character */
    UCHAR      bNlsShift;  /* Shift status (reserved set to zero) */
    USHORT     fsState;    /* Shift state */
    ULONG      time;
    USHORT     fsDD;
    USHORT     fsXlate;
    USHORT     fsShift;
    USHORT     sZero;
} KBDTRANS;

#define INCL_KBD

USHORT rc = KbdXlate(XlateRecord, KbdHandle);

PKBDTRANS XlateRecord; /* Translation Record */
HKBD      KbdHandle;   /* Keyboard handle */

USHORT rc; /* return code */
```

MASM

```
KBDTRANS struc
    kbxl_chChar    db ? ;ASCII character code
    kbxl_chScan    db ? ;scan code
    kbxl_fbStatus  db ? ;State of the character
```

```

kbxl_bNlsShift db ? ;shift status (reserved set to zero)
kbxl_fsState   dw ? ;shift state
kbxl_time      dd ?
kbxl_fsDD      dw ?
kbxl_fsXlate   dw ?
kbxl_fsShift   dw ?
kbxl_sZero     dw ?
    
```

KBDTRANS ends

EXTRN KbdXlate:FAR

INCL_KBD EQU 1

PUSH@ OTHER XlateRecord ;Translation Record


PUSH WORD KbdHandle ;Keyboard handle

CALL KbdXlate

Returns WORD

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOctl DosDevIOctl2
	Signals	DosHoldSignal DosSetSigHandler
KBD	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDSCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · 0 Comments



From:

<http://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:kbdxlate>

Last update: **2021/11/04 13:25**

