

MouGetPtrPos

Bindings: C, MASM

This call queries the mouse driver to determine the current row and column coordinate position of the mouse pointer.

MouGetPtrPos (PtrPos, DeviceHandle)

PtrPos (**PPTRLLOC**) - output Address of the mouse pointer position structure:

pointerrow (**USHORT**) Current pointer row coordinate (pixels or characters).

pointercol (**USHORT**) Current pointer column coordinate (pixels or characters).

DeviceHandle (**HMOU**) - input Contains the handle of the mouse device obtained from a previous *MouOpen*.

rc (**USHORT**) - return Return code descriptions are:

0	NO_ERROR
385	ERROR_MOUSE_NO_DEVICE
466	ERROR_MOU_DETACHED
501	ERROR_MOUSE_NO_CONSOLE
505	ERROR_MOU_EXTENDED_SG

Remarks

For a text window (VIO) application, the text window is a view on the larger logical video buffer (LVB). The mouse pointer can be outside that view and still be within the extent of the LVB. *MouGetPtrPos* then returns the coordinates of the cell under the mouse pointer. If the pointer is outside the LVB image extent, the coordinates of the nearest LVB cell are returned. In either case, the LVB is scrolled until the reported LVB cell appears within the view window.

C bindings

```

typedef struct _PTRLOC { /* moupl */
    USHORT row;           /* pointer row coordinate screen
                           position */
    USHORT col;           /* pointer column coordinate screen
                           position */
} PTRLOC;

#define INCL_MOU

USHORT rc = MouGetPtrPos(PtrPos, DeviceHandle);

PPTRLLOC      PtrPos;      /* Double word structure */
HMOU          DeviceHandle; /* Mouse device handle */

```

USHORT

rc; /* return code */

MASM bindings

```
PTRLLOC  struct
    moupl_row  dw  ? ;pointer row coordinate screen position
    moupl_col  dw  ? ;pointer column coordinate screen position
PTRLLOC  ends
```

```
EXTRN  MouGetPtrPos:FAR
INCL_MOU          EQU 1
```

```
PUSH@ OTHER     PtrPos      ;Double word structure
PUSH    WORD      DeviceHandle ;Mouse device handle
CALL    MouGetPtrPos
```

Returns WORD

From:
<http://185.82.219.184/doku/> - osFree wiki

Permanent link:
<http://185.82.219.184/doku/doku.php?id=en:ibm:prcp:mou:getptrpos>



Last update: **2016/09/15 03:59**